

# Reading Solutions....



## For those with Print Disabilities

*Such as*

- ✓ *Low Vision*
- ✓ *Attention Deficit Disorder, ADD*
- ✓ *Attention-Deficit/Hyperactivity Disorder, ADHD*
- ✓ *Dyslexia*
- ✓ *Literacy Challenges, LD*
- ✓ *English as a Second Language*
- ✓ *And improving general reading and comprehension*

# Scan N Talk Installation

Follow the instructions included in the Colligo CD Case.


**DO NOT PLUG IN SCANNER UNTIL IT TELLS YOU TO.**

With the scanner, read and follow the installation...

“Xerox 7600 Quick Install Guide”

*Add Paper port Icon to your Desk Top when asked for.*

*Now insert the Scan N Talk CD and follow the instructions (Use Run...not Save)*



The screenshot shows a web browser window with the following content:

- Address bar: Colligo Corporation - Microsoft Internet Explorer provided by CenturyTel
- Page title: Scan N Talk Ultra All rights reserved a Colligo product www.colligo.us
- Warning box: Do not hook-up your scanner until the installation program tells you to do so. We recommend that you disable all virus and firewall software before you begin the installation.
- Text: Follow the 3 steps below
- Link: [Install AT&T Natural Voices](#) Vista users need not install.
- Link: [Install ReadText](#)
- Link: [Complete the Installation](#)
- Text: You may now exit



Confirm that **ReadText** icon appears on your Desktop and in the bottom right tool bar **OT** appears.

If not, you will have to probably have to reinstall.

Now that we have installed the scanner and software, we shall tell the scanner buttons what to do.

We shall be using 2 buttons.

The **Archive** button (4<sup>th</sup>) will scan and read back documents to you.

**PHOTO** Button (5<sup>th</sup>) (shown later) allows interactivity with forms and more.

Setting the OCR button

Confirm that **ReadText** icon appears on your Desktop and in the bottom right tool bar, **OT** appears.

# SCAN N TALK™

Setting up **One Touch** reading..... 4th Button **OT**

Close all programs and at the bottom right of your screen is the tool bar




*(Icons , functions match the buttons on the scanner)*

1. From the tool bar, ..... left click on **OT**\*
2. Right click the 4<sup>th</sup> (Archive) button


*\*With Windows 7 the left click may not work, in this case hold down the 4<sup>th</sup> button for 5 seconds)*

# SCAN N TALK™

This window will now appear  
Click and high light all three areas as shown in red



Make sure Notepad stays highlighted and press Refresh



ReadText,  
Scan N Talk  
will appear




Now, APPLY  
and OK




On the prior slide, right side, we saw "Scan US Letter Document". If you desire, you can change from grayscale to color scan, change DPI and contrast.

You will have to unlock/lock your changed settings by clicking the gold padlock/key on the far right.



# SCAN N TALK™

If ReadText/Scan N Talk did not load this is caused by either loading OneTouch after ReadText or if you uninstalled/reinstalled OneTouch... To fix this, Reload the Scan N Talk Installation disk and click on **Complete the Installation**



Colligo Corporation - Microsoft Internet Explorer


**Scan N Talk Ultra** All rights reserved a Colligo product [www.colligo.us](http://www.colligo.us)

Do not hook-up your scanner until the installation program tells you to do so.  
We recommend that you disable all virus and firewall software before you begin the installation.

Follow the 3 steps below

[Install AT&T Natural Voices](#) Vista users need not install.


[Install ReadText](#)

[Complete the Installation](#) 

You may now exit

# SCAN N TALK™

You may also need to follow these steps, as shown on left...click on OPTIONS , it will open the window on right, then select the box beside Text editing applications...apply and OK.  
(By the way, using this feature, you can set any of the other buttons to any application you desire.)



Then apply, OK and follow the steps (if needed as shown before)



# Vista and Windows 7 -64 bit Installation

As shown below, click on Options and the window on the right appears.

In the Step 1 box select the path, enter the command below

C:\Program Files(x86)\ReadText\ReadText.exe

And **Add**



Setting the PHOTO (5<sup>th</sup> button)

From your desktop (or programs) open PaperPort. The "How to Guide" displays, you should read this later to familiarize your self with PaperPort. Exit the guide.

Any program on your computer, i.e. Braille, DAISY books and more can be added to the bottom program icons.

Add ReadText (or any other program not shown by following these steps.

Select TOOLS>NEW PROGRAM LINK

Check TEXT PROGRAM>NEXT

Browse PROGRAM FILES for ReadText, SELECT>SELECT

NEXT>NEXT select Icon from the program, NEXT< NEXT, FINISH

Quit PaperPort and Restart.

Setting the SCAN (5<sup>th</sup> button)      ReadText  has been added.  
THIS ENDS THE INSTALL AND SET UP.

